

Installing OpenType fonts on Windows

Windows: minimum system requirements

- PC using a PentiumPC® processor
- Microsoft Windows® 95, 98 Millennium Edition (ME), Windows NT®4, Windows 2000, Windows XP or Windows Vista
- ATM® Light or Deluxe, version 4.1 or later (not required for Windows 2000 or Windows XP)
- AdobePS printer driver 4.3 or later, if using Windows 95/98/ME with a PostScript printer
- AdobePS printer driver 5.1.2 or later, if using Windows NT®4 with a PostScript printer
- 16MB of ram

Windows: installation on Windows 95/98/ME/NT®4 (requires ATM®Light)

- 1 Choose Start > Programs > Adobe > Adobe Type Manager.
- 2 In the ATM® window, click the Fonts tab.
- 3 Choose Browse For Fonts from the Source pop-up menu.
- 4 Navigate to the folder that contains the fonts you want to install, select the font names. Press the Add button to install the selected fonts.
- 5 Exit ATM®.

Windows: installation on Windows 2000, Windows XP

- 1 Go to Start > Control Panels > Appearance and Themes > Fonts
- 2 In the Fonts window click File, and then click Install New Font. If you don't see the File menu, press ALT.
- 3 In the Add Fonts dialog box, under Drives, click the drive where the font that you want to install is located.
- 4 Under Folders, double-click the folder containing the fonts that you want to add.
- 5 Under List of fonts, click the font that you want to add, and then click Install.

Windows: installation on Windows Vista

- 1 Go to Start > Control Panels > Appearance and Personalization > Fonts
- 2 In the Fonts window click File, and then click Install New Font. If you don't see the File menu, press ALT.
- 3 In the Add Fonts dialog box, under Drives, click the drive where the font that you want to install is located.
- 4 Under Folders, double-click the folder containing the fonts that you want to add.
- 5 Under List of fonts, click the font that you want to add, and then click Install.

Installing OpenType fonts on Macintosh

Macintosh: minimum system requirements

- Macintosh with PowerPC® processor
- Macintosh OS 8.6 to 9.2 or Mac OS X
- ATM® Light or Deluxe, version 4.6 or later (not required for Mac OS X native)
- AdobePS printer driver 8.6 or later recommended if using a PostScript printer with Mac OS 8.6 or 9.2
- 16MB of ram

Macintosh: installation on Mac OS 8.6 to 9.2 and Mac OS X 'Classic'

- 1 Before installing, quit all active applications.
 - 2 Copy or move all the OpenType (.otf) font files into the System Folder/Fonts folder. They must be loose inside this folder, not in a sub-folder.
- If using a Font Management utility, check that OpenType fonts are supported.

Macintosh: installation on Mac OS X native

- 1 Before installing, quit all active applications.
 - 2 Copy or move all the OpenType (.otf) font files into either of the following locations. They must be loose inside this folder, not in a sub-folder.
- [a] <Volume>/Library/Fonts/
NOTE: you must be logged on as an "Administrator" to place fonts in this location. Fonts in this location can be used by any user.
- [b] <Volume>/Users/<username>/Library/Fonts/
• Fonts in this location can only be used by the specified user.

Installing PC TrueType or PC PostScript fonts on Windows

Windows: minimum system requirements

- PC using a Pentium® processor
- Microsoft Windows® 95, 98 Millennium Edition (ME), Windows NT®4, Windows 2000 or Windows XP
- 16MB of ram

Windows: installation on Windows 95/98/ME/NT®4 2000 and Windows XP

- 1 Go to Start > Settings > Control Panels > Fonts
- 2 In the Fonts windows, select the File menu, and choose Install New Font.
- 3 Navigate to the folder that contains the fonts you want to install, select the font names. Press the OK button to install the selected fonts.
- 4 Close the Fonts control panel.

Windows: installation on Windows 2000, Windows XP

- 1 Go to Start > Control Panels > Appearance and Themes > Fonts
- 2 In the Fonts window click File, and then click Install New Font. If you don't see the File menu, press ALT.
- 3 In the Add Fonts dialog box, under Drives, click the drive where the font that you want to install is located.
- 4 Under Folders, double-click the folder containing the fonts that you want to add.
- 5 Under List of fonts, click the font that you want to add, and then click Install.

Windows: installation on Windows Vista

- 1 Go to Start > Control Panels > Appearance and Personalization > Fonts
 - 2 In the Fonts window click File, and then click Install New Font. If you don't see the File menu, press ALT.
 - 3 In the Add Fonts dialog box, under Drives, click the drive where the font that you want to install is located.
 - 4 Under Folders, double-click the folder containing the fonts that you want to add.
 - 5 Under List of fonts, click the font that you want to add, and then click Install.
-